

Angel Handler Application Model Development

Goal: Customized the Appmodel for Angel handler, The Appmodel is developed for handtest automation, it lets Angel handler to communicate with thermostream to control testing temperature and handle with testing parts, make sure 93K system communicate with Angel handler properly and retrieve correct part ID and test temperature for temp cycling and profiling.

Benefit: Customer can VNC Angel handler and 93K system, remotely debug temperature testing without technician help.

Install customized appmodel for angel handler

Customized Application model for angel handler will be supported from qappmodel version 4.6.

Run qapp_install in terminal, specify option -test angel.

term% qapp_install -i testflow.ttf -test angel -rev 4.6

Production test program will be generated: *testflow_handler_angel.tp*.

Applicat file also will be created: *qappmodel_handler_angel_4p6.app*

Soft link is set: *qappmodel_handler_angel_4p6*

testflow_handler_angel.tp

hp93000, testprog, 0.1

Testflow: testflow.ttf

Userproc:

Waferdescr:

Applicdata: qappmodel_handler_angel_4p6.app

Pdi_lib: /opt/hp93000/soc_common/Pdi_lib/exec_input_test


Hp_lib: /opt/hp93000/soc/PH_libs/GenericHandler

Dataform:

Application Model file is linking to the customized angel handler.

Select handler driver for angel handler

sm to start up Smartest and select handler driver for angel handler.



Use synax6 driver for angel handler.

Application Model

START_DIALOG



“Press Start...” dialog

```
{ init:
  ACTIONS
    * APPMODEL_TYPE          = CONST_INPUT(bin);

    EXEC_INP_CALL(qappmodexec setFlags);
    -- MOVE_EVENT_STREAM();    -- Clear Datalog Stream
```


Pre-action and setting system flag: CI_LOG_EVENTS_ENABLE

Application Model

```
LOG_SPECIFICATION
  RESULT_LOG = ON;

{ lot:

  ACTIONS
    -----
    -- GET GENERAL INFORMATION --
    -----
    * PROGRAM      = GET_TEST_INFO (testprog);
    * PROGRAM_REV  = GET_TEST_INFO (test_rev);
    * PROGRAM_DESC = GET_TEST_INFO (test_desc);
    * START_TIME   = GET_TEST_INFO (date_time);
    .
```



Specifies the results are logged, Determines whether the data is logged or not.

Get general information: testflow information, STDF keywords and thermal stream and loops variables.

Application Model

```
-- Launch Perl/Tk GUI --
```

```
EXEC_INP_CALL(qappmodexec getAttributes angel handler);
```

QCT Application Model GUI

File Help

QCT Engineering App Model Rev 4p6

Lot Attribute Window

UID: Angel

Device Name: strider

MCN: CP90-N7415-19

Lot ID: 123

Loadboard: 1042

Parts to Test: 5

DataLog Name:

Operation: Digital

Test Sequence: 0

Sublot: 0

Re-test: 0

Foundry: TSMC

☐ Convert Dlog to SAF

QUIT

Developed by QUALCOMM

CONTINUE

Invoke a function call that will launch Perl Device Window for user to input Lot attribute and device attribute (part ID, testing temperature, sub loop, split etc.) All these info will be saved in temp .xtra file, not log to DTR.

Device Attr - QCT Application Model GUI

File

Device Attribute Window

Site	Package Id	Temperature	SubLoop Cnt	Split
Site 1	45	-55	1	TTT

☐ Redisplay This Window After Iterations.

RETURN

Developed by QUALCOMM


CONTINUE

Application Model

```

-----
-- Read in values from a file --
-----
ATTR_FILE          = FILE_INPUT({DEVICE_DIR}/report/.temp_gappmodel/{USERNAME}.{HOSTNAME});
* TISIRT            = ELEMENT_OF_PARAM_LIST({ATTR_FILE}) / REGEXP (string);
* OPERATOR          = ELEMENT_OF_PARAM_LIST({ATTR_FILE}) / REGEXP (string);
* TESTER            = ELEMENT_OF_PARAM_LIST({ATTR_FILE}) / REGEXP (string);
* OPERATION         = ELEMENT_OF_PARAM_LIST({ATTR_FILE}) / REGEXP (string);
* SEQUENCE          = ELEMENT_OF_PARAM_LIST({ATTR_FILE}) / REGEXP (string);
* THERMAL           = ELEMENT_OF_PARAM_LIST({ATTR_FILE}) / REGEXP (string);
* POSTPROCESS       = ELEMENT_OF_PARAM_LIST({ATTR_FILE}) / REGEXP (string);
* DATABASE          = ELEMENT_OF_PARAM_LIST({ATTR_FILE}) / REGEXP (string);
* DEVICE_NAME       = ELEMENT_OF_PARAM_LIST({ATTR_FILE}) / REGEXP (string);

```




Read in values from created file.

```

-----
-- Generate Directory Structure for saving datalog --
-----
EXEC_INP_CALL(qappmodexec mkDirs {PATH}/report/templates/);
EXEC_INP_CALL(qappmodexec mkDirs {PATH}/report/ascii);
EXEC_INP_CALL(qappmodexec mkDirs {PATH}/report/ascii/{TISIRT});
EXEC_INP_CALL(qappmodexec mkDirs {PATH}/report/bin);
EXEC_INP_CALL(qappmodexec mkDirs {PATH}/report/bin/{TISIRT});
EXEC_INP_CALL(qappmodexec mkDirs {PATH}/report/stdf);
EXEC_INP_CALL(qappmodexec mkDirs {PATH}/report/stdf/{TISIRT});
EXEC_INP_CALL(qappmodexec cleanDirs eng stdf);
EXEC_INP_CALL(qappmodexec cleanDirs eng bin);

```




Generate directory structure for saving datalog.

Application Model

```
-- A call to ph_driver_start is mandatory
PROB_HND_CALL (ph_driver_start);

-- Optionally the handler driver may be reconfigured
-- PROB_HND_CALL (ph_set_configuration debug_level: 1);
PROB_HND_CALL (ph_set_configuration trace_driver_calls: "no");
PROB_HND_CALL (ph_set_configuration driver_message_log: "/tmp/{LOT}.driver_messages" driver_error_log: "/tmp/{LOT}.driver_errors");

-- Optional calls to retrieve information from handler driver
* PH_driver_id   = PROB_HND_CALL (ph_get_id driver);
* PH_plugin_id   = PROB_HND_CALL (ph_get_id plugin);
* PH_equipment_id = PROB_HND_CALL (ph_get_id equipment);
* PH_family      = PROB_HND_CALL (ph_get_configuration handler_family);
* PH_model       = PROB_HND_CALL (ph_get_configuration model);
* PH_plugin      = PROB_HND_CALL (ph_get_configuration driver_plugin);
* PH_config      = PROB_HND_CALL (ph_get_configuration configuration);
```



Starts and initializes handler driver according to the global configuration. Retrieve information from handler driver.

Application Model

```

LOG_SPECIFICATION
  RESULT_LOG = ON;
  -- ASCII Datalog Report File
  NEW_RESULT_FILE = ({PATH}/report/ascii/{TISIRT}/{TISIRT}_{MCN2}-{MCN3}_{LOT}_s{SUBLOT}r{RETEST}s{SEQUENCE}{DLOG_APPEND}dlog);
{ subloop:
  ACTIONS
    SUBLEVEL COUNT no_of_iterations = CONST_INPUT({DEVICE_LOOPCOUNT});
  { DEVICE device:
    ACTIONS
      --EXEC_INP_CALL(qappmodexec setPackageID);
      -- Get a device from the handler
      -- You may measure the handling performance by removing the
      -- comment signs of the ph_timer_start and ph_timer_stop calls
      -- and of the NEW_RESULT_FILE specification below.
      -- ph_timer_start and ph_timer_stop may be nested.
      -- PROB_HND_CALL (ph_timer_start);
      PROB_HND_CALL (ph_device_start);
      -- * PH_get_device_time = PROB_HND_CALL (ph_timer_stop);
      EXEC_INP_CALL(qappmodexec ReadParIDTemperatureWriteXtraFile);
      * SITE1_PART_ID = CONST_INPUT({site1_part_id});
      * SITE1_PART_TXT = CONST_INPUT({site1_part_txt});
      * SITE2_PART_ID = CONST_INPUT({site2_part_id});
      * SITE2_PART_TXT = CONST_INPUT({site2_part_txt});
      * SITE3_PART_ID = CONST_INPUT({site3_part_id});

```

Tells handler to insert devices and waits for test start signal from handler. Call *EXEC_INP_CALL(qappmodexec ReadParIDTemperatureWriteXtraFile)* to retrieve Part ID and temperature from handler for datalogging purpose, these info will overwrite the info in .xtra file.

Application Model

EXEC_INP_CALL(qappmodexec ReadParIDTemperatureWriteXtraFile)

```

else if(strcmp(argv[1], "ReadParIDTemperatureWriteXtraFile") == 0) {
    char tempfilename[200];
    char *filename;
    INST handler;
    char res[32];
    char act_tem[32] = "";
    char act_part[32] = "";
    int length;

    fprintf(stderr, "Retrieve the testing temperature from handler\n");
    handler = iopen("lan[192.168.0.101]:gpib0,6");
    itimeout(handler, 2000);
    iprintf(handler, "TEMP?\n");
    iscanf(handler, "TEMP %s\r\n", &res);
    iclose(handler);
    length = strlen(res);
    strncpy(act_tem, res, length-2);
    fprintf(stderr, "Read back result for TEMP = %s\n", act_tem);

    fprintf(stderr, "Retrieve the testing device ID from handler\n");
    handler = iopen("lan[192.168.0.101]:gpib0,6");
    itimeout(handler, 2000);
    iprintf(handler, "DVID?\n");
    iscanf(handler, "DVID %s\r\n", &res);
    iclose(handler);
    length = strlen(res);
    strncpy(act_part, res, length-2);
    fprintf(stderr, "Read back result for DVID = %s\n", act_part);

    makeXtraFile(tempfilename);
    filename = tempfilename;
    WriteXtraFile(filename, act_part, act_tem);
    readXtraFile(filename, 1);
}

```

Send GPIB command to inquire temperature from handler and retrieve currently testing temperature.

Example:

*Retrieve the testing temperature from handler
Read back result for TEMP = -40*

Send GPIB command to inquire part ID from handler and retrieve currently testing part ID.

Example:

*Retrieve the testing device ID from handler
Read back result for DVID = 004*


Overwrite the temperature and part ID info in the .xtra file and log these info to DTR for datalog purpose.

Application Model

```

LOG_SPECIFICATION
  RESULT_LOG = ON;
  {
    DEVICE_TEST
  }
  -- Reprobe may always be defined,
  -- even if the used handler does not provide reprobing
  REPROBE_ACTION = PROB_HND_CALL(ph_reprobe);
ACTIONS
  -- Clearing package ID
  SET_PACKAGE_ID();
  -- Bin devices
  -- You may measure the handling performance by removing the
  -- comment signs of the ph_timer_start and ph_timer_stop calls.
  -- PROB_HND_CALL (ph_timer_start);
  -- PROB_HND_CALL (ph_device_done);
  -- * PH_bin_device_time = PROB_HND_CALL (ph_timer_stop);
  -- Calling only the Package and temp and split window
  -- EXEC_INP_CALL(qappmodexec setPackageAndTempAndSplit eng);
} -- device
ACTIONS
  PROB_HND_CALL (ph_device_done);
} -- subloop
ACTIONS
  -- close the handler driver
  PROB_HND_CALL (ph_driver_done);
  MOVE_EVENT_STREAM({PATH}/report/bin/{TISIRT}/{TISIRT}_{MCN2}-{MCN3}_{LOT}_s{SUBLOT}r{RETEST}s{SEQUENCE}{DLOG_APPEND}bin);
} -- lot

```



Send a reprobe command to handler, sends the binning data to the handler, terminates the driver.

Customized Application Model Datalog

The customized APP is applied to Dino on Yuzu with SMT7.1.4, we have collected some datalog for several parts' temperature cycling with Site 3 enabled, part ID (001→002→003→004) and each part goes through temperature cycling(25 , -40, 110).



UIDAngel_ND629-90_1234_s0r0s0_172057.stdf



UIDAngel_ND629-90_1234_s0r0s0_172058.dlog